

# 1 User Manual for Simulator\_GUI




Figure 1: Screenshot of the Simulator\_GUI during a typical Schnakenberg simulation.

## 1. What the app simulates (theory in brief)

This app solves two-species reaction-diffusion (RD) systems on a 2D rectangular domain  $\Omega$ :

$$\begin{aligned} \frac{\partial u}{\partial t} &= D_u \Delta u + f(u, v; \theta), \\ \frac{\partial v}{\partial t} &= D_v \Delta v + g(u, v; \theta), \end{aligned} \quad (1)$$

where  $u(\mathbf{x}, t), v(\mathbf{x}, t)$  are concentrations,  $D_u, D_v > 0$  are diffusion coefficients, and  $\Delta$  is the Laplacian. The **same solver pipeline** is used for all models; only  $(f, g)$  changes.

### Schnakenberg model

$$f = a - u + u^2 v, \quad g = b - u^2 v \quad (2)$$

with parameters  $a > 0, b > 0$ . A homogeneous steady state is

$$u_0 = a + b, \quad v_0 = \frac{b}{(a + b)^2}.$$

For suitable  $(a, b, D_u, D_v)$ , diffusion can destabilize the uniform state and create **Turing patterns**.

### Brusselator model

$$f = A - (B + 1)u + u^2 v, \quad g = Bu - u^2 v \quad (3)$$

with parameters  $A > 0, B > 0$ . Homogeneous steady state:

$$u_0 = A, \quad v_0 = \frac{B}{A}.$$

Depending on  $(A, B)$  and diffusion contrast, the system can exhibit stationary patterns and oscillatory regimes.

### Heat test (verification mode)

To validate diffusion and boundary handling, set reactions to zero:

$$f = 0, \quad g = 0 \quad \Rightarrow \quad \frac{\partial u}{\partial t} = D_u \Delta u, \quad \frac{\partial v}{\partial t} = D_v \Delta v.$$

With a localized initial bump, you should observe smoothing/spreading over time.

## What patterns you should expect

- **Spots:** isolated high/low regions (activator peaks).
- **Stripes/Labyrinths:** elongated bands.
- **Complex/Mixed:** combination of spots and stripes; sensitive to parameters and noise.

A large diffusion contrast (often  $D_v \gg D_u$ ) commonly favors Turing-like structures.

## 2. Running the simulation (work-flow)

1. Choose **Model Type**: Schnakenberg, Brusselator, or Heat.
2. Set parameters: **a, b** (or  $A, B$ ), **Du, Dv**, domain and discretization, and time settings.
3. Choose **Initial Condition** and **Noise Amplitude**.
4. Choose **Boundary Conditions**.
5. Choose **Variable to display**, **Plot type**, and **Colormap**.
6. Click **Start/Pause** to run (timer-based), or **Step** for manual stepping.

## 3. Controls and what they do

### Model and Parameters panel

- **Model Type:** selects  $(f, g)$  in Eq. (1). Heat disables reactions for diffusion-only testing.
- **a, b sliders:** reaction parameters (Schnakenberg/Brusselator). Changing these shifts the regime (uniform vs patterns vs oscillations).
- **Du, Dv:** diffusion coefficients. Increasing  $D$  smooths gradients faster. Strong contrast  $D_v/D_u$  can trigger pattern formation.
- **Domain Size:** physical size of the rectangle. Larger domains allow more wavelengths (more spots/stripes).
- **Grid Points:** spatial resolution. Higher improves detail but increases runtime/memory.

- **dt**: time step. Too large can reduce accuracy or stability; too small slows simulation.
- **Total Time**: simulation end time.
- **Update Every N steps**: rendering/refresh interval (performance vs smoothness).

## Initial Conditions and Controls panel

- **Initial Condition**:
  - **Uniform**: starts from constant  $u_0, v_0$  (often add noise to trigger patterns).
  - **Random**: adds random perturbations; helps seed pattern growth.
  - **Localized Spot**: seeds a single region (useful to see spreading / initiation).
- **$u_0$  Base Value,  $v_0$  Base Value**: baseline initial values (often set near steady state).
- **Noise Amplitude**: magnitude of random perturbation; larger noise seeds faster but may distort fine structures.
- **Boundary Conditions**:
  - **Neumann (no-flux)**:  $\partial u / \partial n = \partial v / \partial n = 0$ ; patterns reflect at walls.
  - **Dirichlet**: fixed boundary values (here typically 0); can damp patterns near boundaries.
  - **Periodic**: opposite boundaries are tied; good for “infinite tiling” behavior and cleaner pattern statistics.
- **Buttons**:
  - **Start/Pause**: rebuilds and runs with a timer; pause stops the timer.
  - **Step**: advances by one batch and updates the plot.
  - **Reset**: restores defaults and rebuilds.
  - **Stop**: stops the simulation timer immediately.

## Advanced Features panel

- **Pattern presets** (Turing Spots, Stripes, Complex Patterns): auto-sets parameter combinations (and may lock/unlock inputs) to reproduce typical regimes.
- **Enable real time updates**: updates the plot every step (smoother, but slower).
- **Autoscale color limits**: automatically rescales color range; turning off keeps a fixed scale (better for comparing time frames).
- **Variable to display**:

$$z = \begin{cases} u & \text{display activator} \\ v & \text{display inhibitor} \\ u + v & \text{combined field} \\ \sqrt{u^2 + v^2} & \text{magnitude} \end{cases}$$

- **Plot type** (how your choice changes the visualization):
  - **2D Heatmap**: fastest; color-coded scalar field  $z(\mathbf{x})$  (best for patterns).
  - **3D Surface**: height =  $z$ ; visually intuitive but heavier to render.

- **Contour**: isolines / filled contours; highlights wavelengths and boundaries of spots/stripes.
- **2D Quiver (if enabled)**: vector arrows (typically needs a vector field; if used with scalar  $z$ , define what arrows represent).
- **Colormap**: affects contrast and readability; does not change physics.

## Export and Status panel

- **Simulation Progress**: percentage of  $t/\text{Total Time}$ .
- **Status + Current time**: run state and current  $t$ .
- **History Recording**: must be enabled to save/export; stores frames and solution snapshots.
- **Save Data**: saves current  $(x, y, u, v)$  as CSV or full MAT (with parameters/history).
- **Export Animation**: writes AVI/MP4 from recorded frames. **Frame Rate** controls playback speed.

## 4. Practical tips (so it “looks right”)

- For Schnakenberg, start near  $(u_0, v_0)$  and add small noise; patterns usually emerge gradually.
- If nothing happens: increase diffusion contrast, increase Total Time, or add small noise.
- If plot flickers: enable autoscale (or disable it for consistent comparisons).
- If performance is slow: reduce Grid Points, increase Update Every N steps, or disable real-time updates.
- For verification: choose **Heat** and ensure the bump smooths out without oscillations or patterning.

## 5. Quick reference (one table)

Setting	Effect on result / plot
Model Type	selects kinetics $(f, g)$ ; <b>Heat</b> = diffusion-only
$a, b$ (or $A, B$ )	changes reaction balance; controls regime (uniform/pattern/oscillation)
$D_u, D_v$	smoothing speed; contrast can induce Turing patterns
Domain Size	more space $\Rightarrow$ more pattern wavelengths
Grid Points	resolution/detail vs runtime
$dt$	accuracy/stability vs speed
Initial Condition + Noise	seeds instability; larger noise = faster onset
Boundary Conditions	affects edge behavior and global symmetry
Variable to display	what scalar field is rendered
Plot Type	heatmap/surface/contour change how $z$ is visualized
Autoscale	dynamic color range vs fixed comparisons
History Recording	enables Save/Export